0.1 Exports

The program has four different choices for exporting the obtained data; copy to clipboard, save as image, create LaTeX report and create Microsoft Word report.

Clipboard

Copies the figure to clipboard. Textboxes enable the user to modify title and axis labels before copying.

Image

Saves the image to disk. Textboxes enable the user to modify title and axis labels before copying.

LaTeX

Generates LaTeX report containing the figure. *Image name* textbox enables user to choose file name and format for the figure, which will be saved at the same location as the tex-file. *Caption*, *label* and *width* properties are transferred to corresponding LaTeX commands, while tite and labels are applied directly to the figure before exporting.

Word

Generates Microsoft Word report containing the figure. *Title*, *x-label* and *y-label* overrides the settings of the figure and the caption is inserted on a centred line below.